


## Getting started with "Set Trips to Saved" Delphi version

- 1) Make sure the .system folder is visible on the XT(2).  
<https://www.zumouserforums.co.uk/app.php/ZXT-P84>
- 2) Connect the XT(2) to your PC/Laptop and wait for the device to appear in Windows Explorer.
- 3) Start the program.
- 4) The Zumo XT(2) should be listed. If not you can try 'Refresh devices'.  
See: Screenshot 1
- 5) Double click on the Zumo XT(2)
- 6) Browse to Internal Storage\System\Trips  
See: Screenshot 2
- 7) Click on Check Trips. The program will now check if the trips are imported, or saved. A saved trip will have the checkbox ticked.  
Note: The next time you start the program, it will have remembered your selection, and start rightaway in 'Trips'.
- 8) You can use Shift/Crtrl + mouse click to select multiple lines and click on 'Set selected trips to saved/imported' to change the mImported flag.

Known issue: The first action after you have made a change can take a few seconds. (10-20 secs) Subsequent actions will be fast.

The program copies the trip files to a folder on your hard drive, reads the files, makes changes. And then copies them back to the XT(2). The temp folder is listed on top.

Screenshot 1:



Screenshot 2:

